



Windows PowerShell Get-Help on Cmdlet 'New-AzFederatedIdentityCredential'

PS:\>Get-HELP New-AzFederatedIdentityCredential -Full

NAME

New-AzFederatedIdentityCredential

SYNOPSIS

Create or update a federated identity credential under the specified user assigned identity.

SYNTAX

```
New-AzFederatedIdentityCredential -IdentityName <String> -Name <String> -ResourceGroupName <String>
[-SubscriptionId <String>] [-Audience <String[]>] [-Issuer
<String>] [-Subject <String>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]
[-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Create or update a federated identity credential under the specified user assigned identity.

-IdentityName <String>

The name of the identity resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Name <String>

The name of the federated identity credential resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The Id of the Subscription to which the identity belongs.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Audience <String[]>

The list of audiences that can appear in the issued token.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Issuer <String>

The URL of the issuer to be trusted.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Subject <String>

The identifier of the external identity.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.ManagedServiceIdentity.Models.Api20230131.IFederatedIdentityCredential

----- EXAMPLE 1 -----

PS C:\>New-AzFederatedIdentityCredential -ResourceGroupName azure-rg-test -IdentityName uai-pwsh01 `

-Name fic-pwsh01 -Issuer "https://kubernetes-oauth.azure.com" -Subject "system:serviceaccount:ns:svcaccount"

----- EXAMPLE 2 -----

```
PS C:\>New-AzFederatedIdentityCredential -ResourceGroupName azure-rg-test -IdentityName uai-pwsh01 `
```

```
-Name fic-pwsh01 -Issuer "https://kubernetes-oidc.azure.com" -Subject "system:serviceaccount:ns:svcaccount" `
```

```
-Audience @"api://AzureADTokenExchange-Modified")
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.managedserviceidentity/new-azfederatedidentitycredential>