



Windows PowerShell Get-Help on Cmdlet 'New-AzFrontDoorCdnRuleSocketAddrConditionObject'

PS:\>Get-HELP New-AzFrontDoorCdnRuleSocketAddrConditionObject -Full

NAME

New-AzFrontDoorCdnRuleSocketAddrConditionObject

SYNOPSIS

Create an in-memory object for DeliveryRuleSocketAddrCondition.

SYNTAX

```
New-AzFrontDoorCdnRuleSocketAddrConditionObject -ParameterOperator <SocketAddrOperator> -Name
<MatchVariable> [-ParameterMatchValue <String[]>]
[-ParameterNegateCondition <Boolean>] [-ParameterTransform <Transform[]>] [<CommonParameters>]
```

DESCRIPTION

Create an in-memory object for DeliveryRuleSocketAddrCondition.

PARAMETERS

-ParameterOperator <SocketAddrOperator>

Describes operator to be matched.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Name <MatchVariable>

The name of the condition for the delivery rule.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ParameterMatchValue <String[]>

The match value for the condition of the delivery rule.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ParameterNegateCondition <Boolean>

Describes if this is negate condition or not.

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-ParameterTransform <Transform[]>

List of transforms.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Cdn.Models.Api20240201.DeliveryRuleSocketAddrCondition

----- EXAMPLE 1 -----

```
PS C:\>New-AzFrontDoorCdnRuleSocketAddrConditionObject -Name SocketAddr -ParameterOperator IPMatch  
-ParameterMatchValue 222.10.0.1
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.Cdn/new-AzFrontDoorCdnRuleSocketAddrConditionObject>