



Windows PowerShell Get-Help on Cmdlet 'New-AzFrontDoorLoadBalancingSettingObject'

PS:\>Get-HELP New-AzFrontDoorLoadBalancingSettingObject -Full

NAME

New-AzFrontDoorLoadBalancingSettingObject

SYNOPSIS

Create a PSLoadBalancingSetting object for Front Door creation

SYNTAX

```
New-AzFrontDoorLoadBalancingSettingObject [-AdditionalLatencyInMilliseconds <System.Int32>] [-DefaultProfile  
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name  
<System.String> [-SampleSize <System.Int32>]  
    [-SuccessfulSamplesRequired <System.Int32>] [<CommonParameters>]
```

DESCRIPTION

Create a PSLoadBalancingSetting object for Front Door creation

PARAMETERS

-AdditionalLatencyInMilliseconds <System.Int32>

The additional latency in milliseconds for probes to fall into the lowest latency bucket. Default value is 0

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Name <System.String>

health probe setting name.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-SampleSize <System.Int32>

The number of samples to consider for load balancing decisions. Default value is 4

Required? false
Position? named
Default value None
Accept pipeline input? False

Accept wildcard characters? false

-SuccessfulSamplesRequired <System.Int32>

The number of samples within the sample period that must succeed Default value is 2

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.FrontDoor.Models.PSLoadBalancingSetting

NOTES

New-AzFrontDoorLoadBalancingSettingObject -Name "loadbalancingsetting1"

SampleSize : 4

AdditionalLatencyMilliseconds : 0

SuccessfulSamplesRequired : 2

ResourceState :

Id :

Name : loadbalancingsetting1

Type :

Create a PSLoadBalancingSetting object for Front Door creation

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.frontdoor/new-azfrontdoorloadbalancingsettingobject>

New-AzFrontDoor

Set-AzFrontDoor