



Windows PowerShell Get-Help on Cmdlet 'New-AzKeyVaultCertificateAdministratorDetail'

PS:\>Get-HELP New-AzKeyVaultCertificateAdministratorDetail -Full

NAME

New-AzKeyVaultCertificateAdministratorDetail

SYNOPSIS

Creates an in-memory certificate administrator details object.

SYNTAX

```
New-AzKeyVaultCertificateAdministratorDetail [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-EmailAddress <System.String>] [-FirstName <System.String>] [-LastName <System.String>] [-PhoneNumber
<System.String>] [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The New-AzKeyVaultCertificateAdministratorDetail cmdlet creates an in-memory certificate administrator details object.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-EmailAddress <System.String>

Specifies the email address for the certificate administrator.

Required? false
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-FirstName <System.String>

Specifies the first name of the certificate administrator.

Required? false
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-LastName <System.String>

Specifies the last name of the certificate administrator.

Required? false
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-PhoneNumber <System.String>

Specifies the phone number of the certificate administrator.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateAdministratorDetails

NOTES

- Example 1: Create a certificate administrator details object -

```
$AdminDetails = New-AzKeyVaultCertificateAdministratorDetail -FirstName "Patti" -LastName "Fuller" -EmailAddress  
"patti.fuller@contoso.com" -PhoneNumber "5553334444"  
  
$AdminDetails
```

FirstName	LastName	EmailAddress	PhoneNumber
-----------	----------	--------------	-------------

-----	-----	-----	-----
-------	-------	-------	-------

Patti	Fuller	patti.fuller@contoso.com	5553334444
-------	--------	--------------------------	------------

This command creates an in-memory certificate administrator details object, and then stores it in the \$AdminDetails variable.

Online Version: <https://learn.microsoft.com/powershell/module/az.keyvault/new-azkeyvaultcertificateadministratordetail>

New-AzKeyVaultCertificateOrganizationDetail