



Windows PowerShell Get-Help on Cmdlet 'New-AzNetworkCloudEgressEndpointObject'

PS: \>Get-HELP New-AzNetworkCloudEgressEndpointObject -Full

WARNING: The names of some imported commands from the module 'Az.NetworkCloud.private' include unapproved verbs that might make them less discoverable. To find the

commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

WARNING: The names of some imported commands from the module 'Az.NetworkCloud.private' include unapproved verbs that might make them less discoverable. To find the

commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

WARNING: The names of some imported commands from the module 'Az.NetworkCloud.private' include unapproved verbs that might make them less discoverable. To find the

commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

New-AzNetworkCloudEgressEndpointObject

SYNOPSIS

Create an in-memory object for EgressEndpoint.

SYNTAX

New-AzNetworkCloudEgressEndpointObject -Category <String> -Endpoint <IEndpointDependency[]>

[<CommonParameters>]

DESCRIPTION

Create an in-memory object for EgressEndpoint.

PARAMETERS

-Category <String>

The descriptive category name of endpoints accessible by the AKS agent node.

For example, azure-resource-management, API server, etc.

The platform egress endpoints provided by default will use the category 'default'.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Endpoint <IEndpointDependency[]>

The list of endpoint dependencies.

To construct, see NOTES section for ENDPOINT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.NetworkCloud.Models.Api20230701.EgressEndpoint

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

about_Hash_Tables.

ENDPOINT <IEndpointDependency[]>: The list of endpoint dependencies.

DomainName <String>: The domain name of the dependency.

[Port <Int64?>]: The port of this endpoint.

----- EXAMPLE 1 -----

```
PS C:\>$endpointDependency=New-AzNetworkCloudEndpointDependencyObject -DomainName domainName -Port  
1234
```

```
New-AzNetworkCloudEgressEndpointObject -Category "azure-resource-management" -Endpoint ($endpointDependency)
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/Az.NetworkCloud/new-AzNetworkCloudEgressEndpointObject>