



Windows PowerShell Get-Help on Cmdlet 'New-AzNetworkManagerSubscriptionConnection'

PS:\>Get-HELP New-AzNetworkManagerSubscriptionConnection -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

New-AzNetworkManagerSubscriptionConnection

SYNOPSIS

Creates a network manager subscription connection.

SYNTAX

```
New-AzNetworkManagerSubscriptionConnection [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-Description <System.String>] [-Force] -Name <System.String> -NetworkManagerId <System.String> [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

The New-AzNetworkManagerSubscriptionConnection cmdlet creates a network manager subscription connection.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Description <System.String>

Description.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Do not ask for confirmation if you want to overwrite a resource.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-Name <System.String>

The resource name.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-NetworkManagerId <System.String>

Network Manager Id of the resource you'd like to manage.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Network.Models.NetworkManager.PSNetworkManagerConnection

NOTES

----- Example 1 -----

"/subscriptions/f0dc2b34-dfad-40e4-83e0-2309fed8d00b/resourceGroups/psResourceGroup/providers/Microsoft.Network/networkManagers/psNetworkManager" -Description

"SampleDescription"

NetworkManagerId :

/subscriptions/f0dc2b34-dfad-40e4-83e0-2309fed8d00b/resourceGroups/psResourceGroup/providers/Microsoft.Network/networkManagers/psNetworkManager

ConnectionState : Pending

DisplayName :

Description : SampleDescription

Type : Microsoft.Network/networkManagerConnections

ProvisioningState :

SystemData :

SystemDataText : null

Name : subConnection

Etag :

Id :

/subscriptions/f0dc2b34-dfad-40e4-83e0-2309fed8d00b/providers/Microsoft.Network/networkManagerConnections/subConnection

Creates a network manager connection to a subscription.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/new-aznetworkmanagersubscriptionconnection>

Set-AzNetworkManagerManagementGroupConnection

Get-AzNetworkManagerManagementGroupConnection

Remove-AzNetworkManagerManagementGroupConnection