



Windows PowerShell Get-Help on Cmdlet 'New-AzNetworkWatcherConnectionMonitorEndpointScopeItemObject'

PS:\>Get-HELP New-AzNetworkWatcherConnectionMonitorEndpointScopeItemObject -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

New-AzNetworkWatcherConnectionMonitorEndpointScopeItemObject

SYNOPSIS

Creates a connection monitor endpoint scope item.

SYNTAX

New-AzNetworkWatcherConnectionMonitorEndpointScopeItemObject -Address <System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]

DESCRIPTION

The New-AzNetworkWatcherConnectionMonitorEndpointScopeItemObject cmdlet creates endpoint scope item.

PARAMETERS

-Address <System.String>

The address of the scope item.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSNetworkWatcherConnectionMonitorEndpointScopeItem

NOTES

----- Example 1 -----

New-AzNetworkWatcherConnectionMonitorEndpointScopeItemObject -Address "10.0.1.0/24"

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.network/new-aznetworkwatcherconnectionmonitorendpointscopeitemobject>