



Windows PowerShell Get-Help on Cmdlet 'New-AzRecoveryServicesAsrStorageClassificationMapping'

PS: \>Get-HELP New-AzRecoveryServicesAsrStorageClassificationMapping -Full

NAME

New-AzRecoveryServicesAsrStorageClassificationMapping

SYNOPSIS

Creates an ASR storage classification mapping in the Recovery Services vault.

SYNTAX

```

New-AzRecoveryServicesAsrStorageClassificationMapping [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-Name <System.String> -PrimaryStorageClassification
<Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRStorageClassification> -RecoveryStorageClassification
<Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRStorageClassification> [-Confirm] [-WhatIf]
[<CommonParameters>]

```

DESCRIPTION

The New-AzRecoveryServicesAsrStorageClassificationMapping cmdlet creates a storage classification mapping the Recovery Services vault.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies a name for the ASR storage classification mapping.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PrimaryStorageClassification <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRStorageClassification>

Specifies the primary ASR storage classification object for the mapping.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-RecoveryStorageClassification

<Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRStorageClassification>

Specifies the recovery ASR storage classification object for the mapping.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRStorageClassification

OUTPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRJob

NOTES

----- Example 1 -----

```
$currentJob = New-AzRecoveryServicesAsrStorageClassificationMapping -Name $StorageClassificationMappingName  
-PrimaryStorageClassification  
$PrimaryStorageClassification -RecoveryStorageClassification $RecoveryStorageClassification
```

Starts the storage classification mapping creation operation with the specified parameters and returns the ASR job used to track the operation.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.recoveryservices/new-azrecoveryservicesasrstorageclassificationmapping>

Get-AzRecoveryServicesAsrStorageClassificationMapping

Remove-AzRecoveryServicesAsrStorageClassificationMapping