



Windows PowerShell Get-Help on Cmdlet 'New-AzSqlServerDisasterRecoveryConfiguration'

PS:\>Get-HELP New-AzSqlServerDisasterRecoveryConfiguration -Full

NAME

New-AzSqlServerDisasterRecoveryConfiguration

SYNOPSIS

Creates a database server system recovery configuration.

SYNTAX

```
New-AzSqlServerDisasterRecoveryConfiguration [-ResourceGroupName] <System.String> [-ServerName]
<System.String> [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-FailoverPolicy
<System.String>] -PartnerResourceGroupName <System.String>
-PartnerServerName <System.String> -VirtualEndpointName <System.String> [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

The New-AzSqlServerDisasterRecoveryConfiguration cmdlet creates a SQL database server system recovery configuration.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-FailoverPolicy <System.String>

Specifies the failover policy.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PartnerResourceGroupName <System.String>

Specifies the name of the partner resource group.

Required? true

Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-PartnerServerName <System.String>

Specifies the name of the partner server.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of the resource group.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-ServerName <System.String>

Specifies the name of the server.

Required? true
Position? 1
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-VirtualEndpointName <System.String>

Specifies the name of the virtual end point.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

System.String

OUTPUTS

Microsoft.Azure.Commands.Sql.ServerDisasterRecoveryConfiguration.Model.AzureSqlServerDisasterRecoveryConfigurationModel

NOTES

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.sql/new-azsqlserverdisasterrecoveryconfiguration>

[Get-AzSqlServerDisasterRecoveryConfiguration](#)

[Remove-AzSqlServerDisasterRecoveryConfiguration](#)

[Set-AzSqlServerDisasterRecoveryConfiguration](#)

SQL Database Documentation <https://learn.microsoft.com/azure/sql-database/>