



Windows PowerShell Get-Help on Cmdlet 'New-AzStackHCIVMStoragePath'

PS:\>Get-HELP New-AzStackHCIVMStoragePath -Full

NAME

New-AzStackHCIVMStoragePath

SYNOPSIS

The operation to create or update a storage container.

Please note some properties can be set only during storage container creation.

SYNTAX

```
New-AzStackHCIVMStoragePath -Name <String> -ResourceGroupName <String> [-SubscriptionId <String>] -Location
<String> -Path <String> [-CustomLocationId <String>] [-Tag
    <Hashtable>] [-DefaultProfile <PSObject>] [-AsJob] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-Proxy <Uri>]
[-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

The operation to create or update a storage container.

Please note some properties can be set only during storage container creation.

PARAMETERS

-Name <String>

Name of the storage container

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Location <String>

The geo-location where the resource lives

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Path <String>

Path of the storage container on the disk

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-CustomLocationId <String>

The name of the extended location.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Tag <Hashtable>

Resource tags.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-DefaultProfile <PSObject>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.StackHCIVM.Models.IStorageContainers

----- EXAMPLE 1 -----

```
PS C:\>New-AzStackHCIVMStoragePath -Name "testStoragePath" -ResourceGroupName "test-rg" -CustomLocationId  
"/subscriptions/{subscriptionID}/resourcegroups/{resourceGroupName}/providers/microsoft.extendedlocation/customlocation  
s/{customLocationName}" -Location "eastus" -Path  
"C:\ClusterStorage\Volume1\testpath"
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.stackhcivm/new-azstackhcivmstoragepath>