



Windows PowerShell Get-Help on Cmdlet 'New-AzStorageMoverProject'

PS:\>Get-HELP New-AzStorageMoverProject -Full

NAME

New-AzStorageMoverProject

SYNOPSIS

Creates or updates a Project resource, which is a logical grouping of related jobs.

SYNTAX

```
New-AzStorageMoverProject -Name <String> -ResourceGroupName <String> -StorageMoverName <String>
[-SubscriptionId <String>] [-Description <String>] [-DefaultProfile
<PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy
<Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

```
New-AzStorageMoverProject -Name <String> -ResourceGroupName <String> -StorageMoverName <String>
[-SubscriptionId <String>] -Project <IProject> [-DefaultProfile
<PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy
<Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Creates or updates a Project resource, which is a logical grouping of related jobs.

PARAMETERS

-Name <String>

The name of the Project resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-StorageMoverName <String>

The name of the Storage Mover resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Project <IProject>

The Project resource.

To construct, see NOTES section for PROJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-Description <String>

A description for the Project.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.StorageMover.Models.Api20231001.IProject

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.StorageMover.Models.Api20231001.IProject

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help about_Hash_Tables.

PROJECT <IProject>: The Project resource.

[SystemDataCreatedAt <DateTime?>]: The timestamp of resource creation (UTC).

[SystemDataCreatedBy <String>]: The identity that created the resource.

[SystemDataCreatedByType <CreatedByType?>]: The type of identity that created the resource.

[SystemDataLastModifiedAt <DateTime?>]: The timestamp of resource last modification (UTC)

[SystemDataLastModifiedBy <String>]: The identity that last modified the resource.

[SystemDataLastModifiedByType <CreatedByType?>]: The type of identity that last modified the resource.

[Description <String>]: A description for the Project.

----- EXAMPLE 1 -----

```
PS C:\>New-AzStorageMoverProject -ResourceGroupName myResourceGroup -StorageMoverName myStorageMover  
-Name myProject -Description "description"
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.storage/new-azstoragemoverproject>