



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### **Windows PowerShell Get-Help on Cmdlet 'New-AzSynapseIntegrationRuntimeKey'**

**PS:\>Get-HELP New-AzSynapseIntegrationRuntimeKey -Full**

#### **NAME**

New-AzSynapseIntegrationRuntimeKey

#### **SYNOPSIS**

Regenerate self-hosted integration runtime key.

#### **SYNTAX**

New-AzSynapseIntegrationRuntimeKey [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer> [-Force] -InputObject

<Microsoft.Azure.Commands.Synapse.Models.PSIntegrationRuntime> -KeyName {AuthKey1 | AuthKey2} [-Confirm]

[-WhatIf] [<CommonParameters>]

New-AzSynapseIntegrationRuntimeKey [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer> [-Force] -KeyName

{AuthKey1 | AuthKey2} -Name <System.String> [-ResourceGroupName <System.String>] -WorkspaceName

<System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

New-AzSynapseIntegrationRuntimeKey [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer> [-Force] -KeyName

```

{AuthKey1      |      AuthKey2}      -Name      <System.String>      -WorkspaceObject
<Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace> [-Confirm] [-WhatIf] [<CommonParameters>]

New-AzSynapseIntegrationRuntimeKey      [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -KeyName
{AuthKey1 | AuthKey2} -ResourceId <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

```

## DESCRIPTION

The cmdlet New-AzSynapseIntegrationRuntimeKey regenerates the integration runtime key with the key name specified by 'KeyName' parameter. The previous key will be invalid.

## PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Don't ask for confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

**-InputObject <Microsoft.Azure.Commands.Synapse.Models.PSIntegrationRuntime>**

The integration runtime object.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

**-KeyName <System.String>**

The authentication key name of the self-hosted integration runtime.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

**-Name <System.String>**

The integration runtime name.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

**-ResourceGroupName <System.String>**

Resource group name.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

Resource identifier of Synapse integration runtime.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceName <System.String>

Name of Synapse workspace.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>

workspace input object, usually passed through the pipeline.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false  
Position? named  
Default value False  
Accept pipeline input? False  
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false  
Position? named  
Default value False  
Accept pipeline input? False  
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

## INPUTS

Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace

Microsoft.Azure.Commands.Synapse.Models.PSIIntegrationRuntime

## OUTPUTS

Microsoft.Azure.Commands.Synapse.Models.PSIIntegrationRuntimeKeys

## NOTES

----- Example 1 -----

```
New-AzSynapseIntegrationRuntimeKey -WorkspaceName ContosoWorkspace -Name 'test-selfhost-ir' -KeyName authKey2
```

The cmdlet regenerates key 'authKey2' for integration runtime named 'test-selfhost-ir'.

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.synapse/new-azsynapseintegrationruntimekey>