



Windows PowerShell Get-Help on Cmdlet 'New-AzSynapseKustoPoolAttachedDatabaseConfiguration'

PS:\>Get-HELP New-AzSynapseKustoPoolAttachedDatabaseConfiguration -Full

NAME

New-AzSynapseKustoPoolAttachedDatabaseConfiguration

SYNOPSIS

Creates or updates an attached database configuration.

SYNTAX

```
New-AzSynapseKustoPoolAttachedDatabaseConfiguration -AttachedDatabaseConfigurationName <String>
-KustoPoolName <String> -ResourceGroupName <String> -WorkspaceName
<String> [-SubscriptionId <String>] [-DatabaseName <String>] [-DefaultPrincipalsModificationKind
<DefaultPrincipalsModificationKind>] [-KustoPoolResourceId <String>]
[-Location <String>] [-TableLevelSharingPropertyExternalTablesToExclude <String[]>]
[-TableLevelSharingPropertyExternalTablesToInclude <String[]>]
[-TableLevelSharingPropertyMaterializedViewsToExclude <String[]>]
[-TableLevelSharingPropertyMaterializedViewsToInclude <String[]>]
[-TableLevelSharingPropertyTablesToExclude <String[]>] [-TableLevelSharingPropertyTablesToInclude <String[]>]
[-DefaultProfile <PSObject>] [-AsJob] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-Proxy <Uri>]
[-ProxyCredential <PSCredential>]
```

[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]

DESCRIPTION

Creates or updates an attached database configuration.

PARAMETERS

-AttachedDatabaseConfigurationName <String>

The name of the attached database configuration.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-KustoPoolName <String>

The name of the Kusto pool.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-WorkspaceName <String>

The name of the workspace

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DatabaseName <String>

The name of the database which you would like to attach, use * if you want to follow all current and future databases.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultPrincipalsModificationKind <DefaultPrincipalsModificationKind>

The default principals modification kind

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-KustoPoolResourceId <String>

The resource id of the kusto pool where the databases you would like to attach reside.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Location <String>

Resource location.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-TableLevelSharingPropertyExternalTablesToExclude <String[]>

List of external tables exclude from the follower database

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-TableLevelSharingPropertyExternalTablesToInclude <String[]>

List of external tables to include in the follower database

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-TableLevelSharingPropertyMaterializedViewsToExclude <String[]>

List of materialized views exclude from the follower database

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-TableLevelSharingPropertyMaterializedViewsToInclude <String[]>

List of materialized views to include in the follower database

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-TableLevelSharingPropertyTablesToExclude <String[]>

List of tables to exclude from the follower database

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-TableLevelSharingPropertyTablesToInclude <String[]>

List of tables to include in the follower database

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Synapse.Models.Api20210601Preview.IAttachedDatabaseConfiguration

----- EXAMPLE 1 -----

```
PS C:\>New-AzSynapseKustoPoolAttachedDatabaseConfiguration -ResourceGroupName testrg -WorkspaceName
testws -KustoPoolName testfollowerkustopool -Name
followerconfiguration -KustoPoolResourceId

/subscriptions/00000000-0000-0000-0000-000000000000/resourceGroups/testrg/providers/Microsoft.Synapse/workspaces/t
estws/kustoPools/testkustopool -DatabaseName
testdatabase -DefaultPrincipalsModificationKind Union -Location eastus2
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.synapse/new-azsynapsekustopoolattacheddatabaseconfiguration>