



Windows PowerShell Get-Help on Cmdlet 'New-AzVirtualApplianceAdditionalNicProperty'

PS: \> Get-HELP New-AzVirtualApplianceAdditionalNicProperty -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

New-AzVirtualApplianceAdditionalNicProperty

SYNOPSIS

Define a Network Virtual Appliance Additional Nic Property for the resource.

SYNTAX

```
New-AzVirtualApplianceAdditionalNicProperty [-AddressFamily {IPv4 | IPv6}] [-DefaultProfile  
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -HasPublicIP  
<System.Boolean> -NicName <System.String> [-Confirm] [-WhatIf]  
    [<CommonParameters>]
```

DESCRIPTION

The New-AzVirtualApplianceAdditionalNicProperty command defines an Additional Nic Property for Network Virtual

Appliance resource.

PARAMETERS

-AddressFamily <System.String>

The Address Family for IP for Interface.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-HasPublicIP <System.Boolean>

Additional Interface to have public IP or not.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-NicName <System.String>

The Name of Interface.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSVirtualApplianceAdditionalNicProperties

NOTES

----- Example 1 -----

```
$var=New-AzVirtualApplianceAdditionalNicProperty -NicName "sdwan" -HasPublicIp $true
```

Create an Additional Nic Property object to be used with New-AzNetworkVirtualAppliance command.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/new-azvirtualapplianceadditionalnicproperty>