



Windows PowerShell Get-Help on Cmdlet 'New-AzWebPubSubKey'

PS:\>Get-HELP New-AzWebPubSubKey -Full

NAME

New-AzWebPubSubKey

SYNOPSIS

Regenerate the access key for the resource.

PrimaryKey and SecondaryKey cannot be regenerated at the same time.

SYNTAX

New-AzWebPubSubKey -ResourceGroupName <String> -ResourceName <String> [-SubscriptionId <String>] -KeyType <KeyType> [-DefaultProfile <PSObject>] [-AsJob] [-Break]

[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]

[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]

New-AzWebPubSubKey -InputObject <IWebPubSubIdentity> -KeyType <KeyType> [-DefaultProfile <PSObject>] [-AsJob] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]

[-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]

[<CommonParameters>]

DESCRIPTION

Regenerate the access key for the resource.

PrimaryKey and SecondaryKey cannot be regenerated at the same time.

PARAMETERS

-ResourceGroupName <String>

The name of the resource group that contains the resource.

You can obtain this value from the Azure Resource Manager API or the portal.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceName <String>

The name of the resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

Gets subscription Id which uniquely identify the Microsoft Azure subscription.

The subscription ID forms part of the URI for every service call.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IWebPubSubIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-KeyType <KeyType>

The keyType to regenerate.

Must be either 'primary', 'secondary' or 'salt'(case-insensitive).

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-PassThru [<SwitchParameter>]

Returns true when the command succeeds

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.WebPubSub.Models.IWebPubSubIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.WebPubSub.Models.Api20220801Preview.IWebPubSubKeys

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

about_Hash_Tables.

INPUTOBJECT <IWebPubSubIdentity>: Identity Parameter

[CertificateName <String>]: Custom certificate name

[HubName <String>]: The hub name.

[Id <String>]: Resource identity path

[Location <String>]: the region

[Name <String>]: Custom domain name.

[PrivateEndpointConnectionName <String>]: The name of the private endpoint connection

[ResourceGroupName <String>]: The name of the resource group that contains the resource. You can obtain this value from the Azure Resource Manager API or the portal.

[ResourceName <String>]: The name of the resource.

[SharedPrivateLinkResourceName <String>]: The name of the shared private link resource

[SubscriptionId <String>]: Gets subscription Id which uniquely identify the Microsoft Azure subscription. The subscription ID forms part of the URI for every service call.

----- EXAMPLE 1 -----

```
PS C:\>New-AzWebPubSubKey -ResourceGroupName psdemo -ResourceName psdemo-wps -KeyType 'Primary' |  
Format-List
```

----- EXAMPLE 2 -----

```
PS C:\>$wps = Get-AzWebPubSub -Name psdemo-wps -ResourceGroupName psdemo
```

```
$wps | New-AzWebPubSubKey -KeyType Primary | Format-List
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.signalr/new-azwebpubsubkey>