



Windows PowerShell Get-Help on Cmdlet 'New-AzWvdScalingPlanPooledSchedule'

PS:\>Get-HELP New-AzWvdScalingPlanPooledSchedule -Full

NAME

New-AzWvdScalingPlanPooledSchedule

SYNOPSIS

Create or update a ScalingPlanPooledSchedule.

SYNTAX

```
New-AzWvdScalingPlanPooledSchedule -ResourceGroupName <String> -ScalingPlanName <String>
-ScalingPlanScheduleName <String> [-SubscriptionId <String>] [-DaysOfWeek
<DayOfWeek[]>] [-OffPeakLoadBalancingAlgorithm <SessionHostLoadBalancingAlgorithm>] [-OffPeakStartTimeHour
<Int32>] [-OffPeakStartTimeMinute <Int32>]
[-PeakLoadBalancingAlgorithm <SessionHostLoadBalancingAlgorithm>] [-PeakStartTimeHour <Int32>]
[-PeakStartTimeMinute <Int32>] [-RampDownCapacityThresholdPct <Int32>]
[-RampDownForceLogoffUser] [-RampDownLoadBalancingAlgorithm <SessionHostLoadBalancingAlgorithm>]
[-RampDownMinimumHostsPct <Int32>] [-RampDownNotificationMessage
<String>] [-RampDownStartTimeHour <Int32>] [-RampDownStartTimeMinute <Int32>] [-RampDownStopHostsWhen
<StopHostsWhen>] [-RampDownWaitTimeMinute <Int32>]
[-RampUpCapacityThresholdPct <Int32>] [-RampUpLoadBalancingAlgorithm <SessionHostLoadBalancingAlgorithm>]
[-RampUpMinimumHostsPct <Int32>] [-RampUpStartTimeHour
```

<Int32>] [-RampUpStartTimeMinute <Int32>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend
 <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>]
 [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]
 [<CommonParameters>]

DESCRIPTION

Create or update a ScalingPlanPooledSchedule.

PARAMETERS

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ScalingPlanName <String>

The name of the scaling plan.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ScalingPlanScheduleName <String>

The name of the ScalingPlanSchedule

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-DaysOfWeek <DayOfWeek[]>

Set of days of the week on which this schedule is active.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-OffPeakLoadBalancingAlgorithm <SessionHostLoadBalancingAlgorithm>

Load balancing algorithm for off-peak period.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-OffPeakStartTimeHour <Int32>

The hour.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-OffPeakStartTimeMinute <Int32>

The minute.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-PeakLoadBalancingAlgorithm <SessionHostLoadBalancingAlgorithm>

Load balancing algorithm for peak period.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-PeakStartTimeHour <Int32>

The hour.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-PeakStartTimeMinute <Int32>

The minute.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-RampDownCapacityThresholdPct <Int32>

Capacity threshold for ramp down period.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-RampDownForceLogoffUser [<SwitchParameter>]

Should users be logged off forcefully from hosts.

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-RampDownLoadBalancingAlgorithm <SessionHostLoadBalancingAlgorithm>

Load balancing algorithm for ramp down period.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-RampDownMinimumHostsPct <Int32>

Minimum host percentage for ramp down period.

Required? false
Position? named
Default value 0
Accept pipeline input? false
Accept wildcard characters? false

-RampDownNotificationMessage <String>

Notification message for users during ramp down period.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-RampDownStartTimeHour <Int32>

The hour.

Required? false
Position? named
Default value 0
Accept pipeline input? false
Accept wildcard characters? false

-RampDownStartTimeMinute <Int32>

The minute.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-RampDownStopHostsWhen <StopHostsWhen>

Specifies when to stop hosts during ramp down period.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-RampDownWaitTimeMinute <Int32>

Number of minutes to wait to stop hosts during ramp down period.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-RampUpCapacityThresholdPct <Int32>

Capacity threshold for ramp up period.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-RampUpLoadBalancingAlgorithm <SessionHostLoadBalancingAlgorithm>

Load balancing algorithm for ramp up period.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-RampUpMinimumHostsPct <Int32>

Minimum host percentage for ramp up period.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-RampUpStartTimeHour <Int32>

The hour.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-RampUpStartTimeMinute <Int32>

The minute.

Required? false
Position? named
Default value 0
Accept pipeline input? false
Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False
Accept pipeline input? false
Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,
ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.DesktopVirtualization.Models.Api20230905.IScalingPlanPooledSchedule

PS C:\>New-AzWvdScalingPlanPooledSchedule -ResourceGroupName rgName `

-ScalingPlanName spName `

-ScalingPlanScheduleName scheduleName `

-DaysOfWeek @('Monday', 'Tuesday', 'Wednesday', 'Thursday', 'Friday') `

-RampUpStartTimeHour 6 `

-RampUpStartTimeMinute 30 `

-RampUpLoadBalancingAlgorithm BreadthFirst `

-RampUpMinimumHostsPct 20 `

-RampUpCapacityThresholdPct 20 `

-PeakStartTimeHour 8 `

-PeakStartTimeMinute 30 `

-PeakLoadBalancingAlgorithm DepthFirst `

-RampDownStartTimeHour 16 `

-RampDownStartTimeMinute 0 `

-RampDownLoadBalancingAlgorithm BreadthFirst `

-RampDownMinimumHostsPct 20 `

-RampDownCapacityThresholdPct 20 `

-RampDownForceLogoffUser:\$true `

-RampDownWaitTimeMinute 30 `

-RampDownNotificationMessage "Log out now, please." `

-RampDownStopHostsWhen ZeroSessions `

-OffPeakStartTimeHour 22 `

-OffPeakStartTimeMinute 45 `

-OffPeakLoadBalancingAlgorithm DepthFirst

RELATED LINKS

