



Windows PowerShell Get-Help on Cmdlet 'New-SmbClientCertificateMapping'

PS:\>Get-HELP New-SmbClientCertificateMapping -Full

NAME

New-SmbClientCertificateMapping

SYNTAX

New-SmbClientCertificateMapping [-Namespace] <string> [-Thumbprint <string>] [-StoreName <string>] [-IssuerName <string>] [-Subject <string>] [-DisplayName <string>]

[-Type {QUIC}] [-Flags {None}] [-Force] [-CimSession <CimSession[]>] [-ThrottleLimit <int>] [-AsJob] [-WhatIf] [-Confirm]

[<CommonParameters>]

PARAMETERS

-AsJob

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1
Aliases	None
Dynamic?	false

-CimSession <CimSession[]>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1
Aliases	Session
Dynamic?	false

-Confirm

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	cf
Dynamic?	false

-DisplayName <string>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1
Aliases	None
Dynamic?	false

-Flags <Flags>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1

Aliases	None
Dynamic?	false

-Force

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1
Aliases	None
Dynamic?	false

-IssuerName <string>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1
Aliases	None
Dynamic?	false

-Namespace <string>

Required?	true
Position?	1
Accept pipeline input?	true (ByPropertyName)
Parameter set name	AddClientCertificateMapping1
Aliases	None
Dynamic?	false

-StoreName <string>

Required?	false
-----------	-------

Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1
Aliases	None
Dynamic?	false

-Subject <string>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1
Aliases	None
Dynamic?	false

-ThrottleLimit <int>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1
Aliases	None
Dynamic?	false

-Thumbprint <string>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1
Aliases	None
Dynamic?	false

-Type <Type>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	AddClientCertificateMapping1
Aliases	None
Dynamic?	false

-WhatIf

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	wi
Dynamic?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Management.Infrastructure.CimInstance

ALIASES

nsmbccm

REMARKS

Get-Help cannot find the Help files for this cmdlet on this computer. It is displaying only partial help.

-- To download and install Help files for the module that includes this cmdlet, use Update-Help.