



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Remove-AzApplicationGatewayListener'***

**PS:\>Get-HELP Remove-AzApplicationGatewayListener -Full**

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

#### **NAME**

Remove-AzApplicationGatewayListener

#### **SYNOPSIS**

Removes a TCP\TLS listener from an application gateway.

#### **SYNTAX**

Remove-AzApplicationGatewayListener                            -ApplicationGateway

<Microsoft.Azure.Commands.Network.Models.PSApplicationGateway> [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>    -Name

<System.String> [<CommonParameters>]

#### **DESCRIPTION**

The Remove-AzApplicationGatewayListener cmdlet removes a TCP\TLS listener from an Azure application gateway.

## PARAMETERS

-ApplicationGateway <Microsoft.Azure.Commands.Network.Models.PSApplicationGateway>

The applicationGateway

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The name of the application gateway listener

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

`OutBuffer`, `PipelineVariable`, and `OutVariable`. For more information, see [about\\_CommonParameters](#) (<https://go.microsoft.com/fwlink/?LinkId=113216>).

## INPUTS

`Microsoft.Azure.Commands.Network.Models.PSApplicationGateway`

## OUTPUTS

`Microsoft.Azure.Commands.Network.Models.PSApplicationGateway`

## NOTES

-- Example 1: Remove an application gateway TCP\TLS listener --

```
$AppGw = Get-AzApplicationGateway -Name "ApplicationGateway01" -ResourceGroupName "ResourceGroup01"
Remove-AzApplicationGatewayListener -ApplicationGateway $AppGw -Name "Listener02"
Set-AzApplicationGateway -ApplicationGateway $AppGW
```

The first command gets an application gateway and stores it in the `$AppGw` variable. The second command removes the TCP\TLS listener named Listener02 from the application gateway stored in `$AppGw`. The last command updates the application gateway.

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/remove-azapplicationgatewaylistener>

`Add-AzApplicationGatewayListener`

Page 3/4

Get-AzApplicationGatewayListener

New-AzApplicationGatewayListener

Set-AzApplicationGatewayListener