



Windows PowerShell Get-Help on Cmdlet 'Remove-AzApplicationGatewayTrustedClientCertificate'

PS: \> Get-HELP Remove-AzApplicationGatewayTrustedClientCertificate -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzApplicationGatewayTrustedClientCertificate

SYNOPSIS

Removes the trusted client CA certificate chain object from an application gateway.

SYNTAX

```
Remove-AzApplicationGatewayTrustedClientCertificate -ApplicationGateway
<Microsoft.Azure.Commands.Network.Models.PSApplicationGateway> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name
<System.String> [<CommonParameters>]
```

DESCRIPTION

The Remove-AzApplicationGatewayTrustedClientCertificate cmdlet removes the trusted client CA certificate chain object

from an application gateway.

PARAMETERS

-ApplicationGateway <Microsoft.Azure.Commands.Network.Models.PSApplicationGateway>

The applicationGateway

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The name of the trusted client CA certificate chain

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSApplicationGateway

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSApplicationGateway

NOTES

----- Example 1 -----

```
$gw = Get-AzApplicationGateway -Name $appgwName -ResourceGroupName $resgpName
```

```
    $gw = Remove-AzApplicationGatewayTrustedClientCertificate -ApplicationGateway $gw -Name  
"TrustedClientCertificate01"
```

```
Set-AzApplicationGateway -ApplicationGateway $gw
```

The first command gets an application gateway and stores it in the \$gw variable. The second command removes the
trusted client CA certificate chain named

"TrustedClientCertificate01" from the application gateway stored in \$gw. The last command updates the application
gateway.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.network/remove-azapplicationgatewaytrustedclientcertificate>

New-AzApplicationGatewayTrustedClientCertificate

Add-AzApplicationGatewayTrustedClientCertificate

Get-AzApplicationGatewayTrustedClientCertificate

Set-AzApplicationGatewayTrustedClientCertificate