



Windows PowerShell Get-Help on Cmdlet 'Remove-AzAutomationConnectionType'

PS:\>Get-HELP Remove-AzAutomationConnectionType -Full

NAME

Remove-AzAutomationConnectionType

SYNOPSIS

Removes an Automation connection type.

SYNTAX

```
Remove-AzAutomationConnectionType [-ResourceGroupName] <System.String> [-AutomationAccountName]
<System.String> [-Name] <System.String> [[-Force]] [-DefaultProfile]
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

The Remove-AzAutomationConnectionType cmdlet removes a connection type from Azure Automation. All connections that are associated with the connection type that you delete become unusable. Remove them, unless you create a new connection type that meets the following criteria: - The type has the same name as the original connection type.

- The type has the same field definitions as the original connection type.

It can have additional fields.

PARAMETERS

-AutomationAccountName <System.String>

Specifies the name of the Automation account for which this cmdlet removes a connection type.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

ps_force

Required? false

Position? 3

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the Automation connection type that this cmdlet removes.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of the resource group from which this cmdlet removes an Automation connection type.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

System.Void

NOTES

----- Example 1: Remove a connection type -----

```
Remove-AzAutomationConnectionType -AutomationAccountName "Contoso17" -Name "ContosoConnectionType"
-ResourceGroupName "ResourceGroup01"
```

This command removes a connection type named ContosoConnectionType in the Automation account named Contoso17.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.automation/remove-azautomationconnectiontype>

Remove-AzAutomationConnection