



Windows PowerShell Get-Help on Cmdlet 'Remove-AzAutomationDscConfiguration'

PS:\>Get-HELP Remove-AzAutomationDscConfiguration -Full

NAME

Remove-AzAutomationDscConfiguration

SYNOPSIS

Removes DSC configurations from Automation.

SYNTAX

```
Remove-AzAutomationDscConfiguration [-ResourceGroupName] <System.String> [-AutomationAccountName]
<System.String> [-Name] <System.String> [[-Force]] [-DefaultProfile]
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

The Remove-AzAutomationDscConfiguration cmdlet removes APS Desired State Configuration (DSC) configurations from Azure Automation.

-AutomationAccountName <System.String>

Specifies the name of the Automation account that contains DSC configurations that this cmdlet removes.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

ps_force

Required? false

Position? 3

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the DSC configuration that this cmdlet removes.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of a resource group for which this cmdlet gets DSC configurations.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

System.Void

NOTES

----- Example 1 -----

```
Remove-AzAutomationDscConfiguration -AutomationAccountName 'AutomationAccount01' -Name 'Configuration01'  
-ResourceGroupName myresourcegroup
```

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.automation/remove-azautomationdscconfiguration>

Export-AzAutomationDscConfiguration

Get-AzAutomationDscConfiguration

Import-AzAutomationDscConfiguration

