



Windows PowerShell Get-Help on Cmdlet 'Remove-AzAutomationModule'

PS:\>Get-HELP Remove-AzAutomationModule -Full

NAME

Remove-AzAutomationModule

SYNOPSIS

Removes a module from Automation.

SYNTAX

```
Remove-AzAutomationModule [-ResourceGroupName] <System.String> [-AutomationAccountName] <System.String>
[-Name] <System.String> [[-Force]] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-RuntimeVersion
{5.1 | 7.2}] [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzAutomationModule cmdlet removes a module from an Automation account in Azure Automation.

PARAMETERS

-AutomationAccountName <System.String>

Specifies the name of the Automation account from which this cmdlet removes a module.

Required?	true
Position?	1
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Force <System.Management.Automation.SwitchParameter>

ps_force

Required?	false
Position?	3
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-Name <System.String>

Specifies the name of the module that this cmdlet removes.

Required?	true
Position?	2
Default value	None
Accept pipeline input?	True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of a resource group in which this cmdlet removes a module.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-RuntimeVersion <System.String>

Runtime Environment of module

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

OUTPUTS

System.Void

NOTES

----- Example 1: Remove a module -----

```
Remove-AzAutomationModule -AutomationAccountName "Contoso17" -Name "ContosoModule" -ResourceGroupName "ResourceGroup01"
```

This command removes a module named ContosoModule from the Automation account named Contoso17.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.automation/remove-azautomationmodule>

[Get-AzAutomationModule](#)

[New-AzAutomationModule](#)

[Set-AzAutomationModule](#)