



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Remove-AzCapacityReservation'***

**PS:\>Get-HELP Remove-AzCapacityReservation -Full**

#### **NAME**

Remove-AzCapacityReservation

#### **SYNOPSIS**

Removes a Capacity Reservation resource

#### **SYNTAX**

Remove-AzCapacityReservation                    [-AsJob]                    [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name

  <System.String>] -ReservationGroupName <System.String> -ResourceGroupName <System.String> [-Confirm] [-WhatIf]

[<CommonParameters>]

#### **DESCRIPTION**

The Remove-AzCapacityReservation cmdlet removes a Capacity Reservation resource

#### **PARAMETERS**

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false  
Position? named  
Default value False  
Accept pipeline input? False  
Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false  
Position? named  
Default value None  
Accept pipeline input? False  
Accept wildcard characters? false

-Name <System.String>

Specifies the name of the capacity reservation resource.

Required? false  
Position? named  
Default value None  
Accept pipeline input? True (ByPropertyName)  
Accept wildcard characters? true

-ReservationGroupName <System.String>

Specifies the name of the capacity reservation group.

Required? true  
Position? named  
Default value None  
Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? true

-ResourceGroupName <System.String>

Specifies the name of a resource group.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## INPUTS

System.String

## OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSOperationStatusResponse

## NOTES

### ----- Example 1 -----

```
Remove-AzCapacityReservation -ResourceGroupName "myRG" -ReservationGroupName  
"myCapacityReservationGroup" -Name "myCapacityReservation"
```

This command removes the Capacity Reservation resource.

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/remove-azcapacityreservation>