



Windows PowerShell Get-Help on Cmdlet 'Remove-AzCapacityReservationGroup'

PS:\>Get-HELP Remove-AzCapacityReservationGroup -Full

NAME

Remove-AzCapacityReservationGroup

SYNOPSIS

Removes a Capacity Reservation Group

SYNTAX

```

Remove-AzCapacityReservationGroup [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
<Microsoft.Azure.Commands.Compute.Automation.Models.PSCapacityReservationGroup> [-Confirm] [-WhatIf]
[<CommonParameters>]

```

```

Remove-AzCapacityReservationGroup [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name
<System.String> -ResourceGroupName <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

```

```

Remove-AzCapacityReservationGroup [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -ResourceId
<System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

```

DESCRIPTION

The Remove-AzCapacityReservationGroup cmdlet removes a Capacity Reservation Group

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Compute.Automation.Models.PSCapacityReservationGroup>

PowerShell capacity reservation group object

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the capacity reservation group.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of a resource group.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceId <System.String>

Resource ID for your capacity reservation group.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,
ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.Compute.Automation.Models.PSCapacityReservationGroup

OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSOperationStatusResponse

----- Example 1 -----

```
Remove-AzCapacityReservationGroup -ResourceGroupName "myRG" -Name "myCapacityReservationGroup"
```

This command removes the Capacity Reservation Group.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/remove-azcapacityreservationgroup>