



Windows PowerShell Get-Help on Cmdlet 'Remove-AzContext'

PS:\>Get-HELP Remove-AzContext -Full

NAME

Remove-AzContext

SYNOPSIS

Remove a context from the set of available contexts

SYNTAX

```

Remove-AzContext [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -InputObject
<Microsoft.Azure.Commands.Profile.Models.Core.PSAzureContext> [-PassThru] [-Scope {Process | CurrentUser}]
[-Confirm] [-WhatIf] [<CommonParameters>]

```

```

Remove-AzContext [-Name] <System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force]
[-PassThru] [-Scope {Process | CurrentUser}] [-Confirm] [-WhatIf] [<CommonParameters>]

```

DESCRIPTION

Remove an azure context from the set of contexts

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, tenant and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Remove context even if it is the default

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Profile.Models.Core.PSAzureContext>

A context object, normally passed through the pipeline.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

The name of the context

Required? true
Position? 0
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Return the removed context

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-Scope <Microsoft.Azure.Commands.Profile.Common.ContextModificationScope>

Determines the scope of context changes, for example, whether changes apply only to the current process, or to all sessions started by this user

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Profile.Models.Core.PSAzureContext

OUTPUTS

Microsoft.Azure.Commands.Profile.Models.Core.PSAzureContext

NOTES

----- Example 1 -----

Remove-AzContext -Name Default

Remove the context named default

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.accounts/remove-azcontext>