



Windows PowerShell Get-Help on Cmdlet 'Remove-AzCosmosDBSqlRoleAssignment'

PS:\>Get-HELP Remove-AzCosmosDBSqlRoleAssignment -Full

NAME

Remove-AzCosmosDBSqlRoleAssignment

SYNOPSIS

Deletes the CosmosDB Sql Role Assignment.

SYNTAX

```
Remove-AzCosmosDBSqlRoleAssignment -AccountName <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Id <System.String>
[-PassThru] -ResourceGroupName <System.String>
    [-Confirm] [-WhatIf] [<CommonParameters>]

Remove-AzCosmosDBSqlRoleAssignment [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Id <System.String>
    -ParentObject <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults> [-PassThru] [-Confirm]
[-WhatIf] [<CommonParameters>]
```

```
Remove-AzCosmosDBSqlRoleAssignment [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject Page 1/5
```

<Microsoft.Azure.Commands.CosmosDB.Models.PSSqlRoleAssignmentGetResults> [-PassThru] [-Confirm] [-WhatIf]
[<CommonParameters>]

DESCRIPTION

The Remove-AzCosmosDBSqlRoleAssignment cmdlet deletes the CosmosDB Sql Role Assignment corresponding to the given ResourceGroupName, AccountName and Id. Id can be either fully qualified or just the Guid.

PARAMETERS

-AccountName <System.String>

Name of the Cosmos DB database account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Id <System.String>

Role Assignment Id.

Required? true

Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.CosmosDB.Models.PSSqlRoleAssignmentGetResults>

Role assignment object.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-ParentObject <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults>

CosmosDB Account object

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

To be set to true if the user wants to receive an output. The output is true if the operation was successful and an error is thrown if not.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of resource group.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSSqlRoleAssignmentGetResults

OUTPUTS

System.Void

NOTES

----- Example 1 -----

```
Remove-AzCosmosDBSqlRoleAssignment -ResourceGroupName resourceGroupName -AccountName accountName -Id  
id -PassThru
```

true

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.cosmosdb/remove-azcosmosdbsqlroleassignment>