



Windows PowerShell Get-Help on Cmdlet 'Remove-AzCosmosDBSqlTrigger'

PS:\>Get-HELP Remove-AzCosmosDBSqlTrigger -Full

NAME

Remove-AzCosmosDBSqlTrigger

SYNOPSIS

Deletes the CosmosDB Sql Trigger.

SYNTAX

```
Remove-AzCosmosDBSqlTrigger -AccountName <System.String> -ContainerName <System.String> -DatabaseName
<System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name
<System.String> [-PassThru] -ResourceGroupName <System.String>
    [-Confirm] [-WhatIf] [<CommonParameters>]
```

Remove-AzCosmosDBSqlTrigger [-DefaultProfile
 <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
 <Microsoft.Azure.Commands.CosmosDB.Models.PSSqlTriggerGetResults> [-PassThru] [-Confirm] [-WhatIf]
 [<CommonParameters>]

DESCRIPTION

The Remove-AzCosmosDBSqlTrigger cmdlet deletes the CosmosDB Sql Trigger corresponding to the given ResourceGroupName, AccountName and DatabaseName.

PARAMETERS

-AccountName <System.String>

Name of the Cosmos DB database account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ContainerName <System.String>

Container name.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DatabaseName <System.String>

Database name.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.CosmosDB.Models.PSSqlTriggerGetResults>

Sql trigger Object

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Trigger name.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

To be set to true if the user wants to receive an output. The output is true if the operation was successful and an error is thrown if not.

Required? false

Position? named

Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of resource group.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

System.Void

System.Boolean

NOTES

----- Example 1 -----

```
Remove-AzCosmosDBSqlTrigger -ResourceGroupName "resourceGroupName" -AccountName "accountName"  
-DatabaseName "databaseName" -ContainerName "containerName" -Name  
"triggerName"
```

