



Windows PowerShell Get-Help on Cmdlet 'Remove-AzDataBoxEdgeOrder'

PS:\>Get-HELP Remove-AzDataBoxEdgeOrder -Full

NAME

Remove-AzDataBoxEdgeOrder

SYNOPSIS

Removes the order for a device.

SYNTAX

```
Remove-AzDataBoxEdgeOrder [-ResourceGroupName] <System.String> [-DeviceName] <System.String> [-AsJob]
[-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Remove-AzDataBoxEdgeOrder [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
    <Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeOrder> [-PassThru] [-Confirm] [-WhatIf]
    [<CommonParameters>]
```

```
Remove-AzDataBoxEdgeOrder [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
```

-ResourceId

<System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

The Remove-AzDataBoxEdgeOrder cmdlet deletes an existing order for a Data Box Edge device.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DeviceName <System.String>

Device Name

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-InputObject <Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeOrder>

Input Object

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

returns true if successful

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource Group Name

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceId <System.String>

Azure ResourceId

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeOrder

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeOrder

NOTES

----- Example 1 -----

Remove-AzDataBoxEdgeOrder -ResourceGroupName resourceGroupName -DeviceName deviceName

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.databoxedge/remove-azdataboxedgeorder>