



Windows PowerShell Get-Help on Cmdlet 'Remove-AzDataFactoryHub'

PS:\>Get-HELP Remove-AzDataFactoryHub -Full

NAME

Remove-AzDataFactoryHub

SYNTAX

```
Remove-AzDataFactoryHub [-ResourceGroupName] <string> [-DataFactoryName] <string> [-Name] <string> [-Force]
[-DefaultProfile <IAzureContextContainer>] [-WhatIf]
[-Confirm] [<CommonParameters>]
```

```
Remove-AzDataFactoryHub [-DataFactory] <PSDataFactory> [-Name] <string> [-Force] [-DefaultProfile
<IAzureContextContainer>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

PARAMETERS

-Confirm

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	cf

Dynamic? false

-DataFactory <PSDataFactory>

The data factory object.

Required? true

Position? 0

Accept pipeline input? true (ByPropertyName)

Parameter set name ByFactoryObject

Aliases None

Dynamic? false

-DataFactoryName <string>

The data factory name.

Required? true

Position? 1

Accept pipeline input? true (ByPropertyName)

Parameter set name ByFactoryName

Aliases None

Dynamic? false

-DefaultProfile <IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? Named

Accept pipeline input? false

Parameter set name (All)

Aliases AzContext, AzureRmContext, AzureCredential

Dynamic? false

-Force

Don't ask for confirmation.

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	None
Dynamic?	false

-Name <string>

The hub name.

Required?	true
Position?	2
Accept pipeline input?	true (ByPropertyName)
Parameter set name	(All)
Aliases	HubName
Dynamic?	false

-ResourceGroupName <string>

The resource group name.

Required?	true
Position?	0
Accept pipeline input?	true (ByPropertyName)
Parameter set name	ByFactoryName
Aliases	None
Dynamic?	false

-WhatIf

Required?	false
Position?	Named

Accept pipeline input?	false
Parameter set name	(All)
Aliases	wi
Dynamic?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String
Microsoft.Azure.Commands.DataFactories.Models.PSDataFactory

OUTPUTS

System.Boolean

ALIASES

None

REMARKS

None