



Windows PowerShell Get-Help on Cmdlet 'Remove-AzDataFactoryV2TriggerSubscription'

PS:\>Get-HELP Remove-AzDataFactoryV2TriggerSubscription -Full

NAME

Remove-AzDataFactoryV2TriggerSubscription

SYNOPSIS

Unsubscribe the event trigger to external service events.

SYNTAX

```
Remove-AzDataFactoryV2TriggerSubscription [-ResourceGroupName] <String> [-DataFactoryName] <String> [-Name]
<String> [-DefaultProfile <IAzureContextContainer>]
[-Force] [-PassThru] [-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Remove-AzDataFactoryV2TriggerSubscription [-InputObject] <PSTrigger> [-DefaultProfile <IAzureContextContainer>]
[-Force] [-PassThru] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```
Remove-AzDataFactoryV2TriggerSubscription [-ResourceId] <String> [-DefaultProfile <IAzureContextContainer>]
[-Force] [-PassThru] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

This command unsubscribes the event trigger to the specified external service events from the trigger definition.

PARAMETERS

-DataFactoryName <String>

The data factory name.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force [<SwitchParameter>]

Don't ask for confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <PSTrigger>

The trigger object.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <String>

The trigger name.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-PassThru [<SwitchParameter>]

If specified, cmdlet will return true on successful delete.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <String>

The resource group name.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceId <String>

The Azure resource ID.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.DataFactoryV2.Models.PSTrigger

OUTPUTS

Microsoft.Azure.Commands.DataFactoryV2.Models.PSTriggerSubscriptionStatus

NOTES

----- Example 1 -----

Remove-AzDataFactoryV2TriggerSubscription -ResourceGroupName ADF -DataFactoryName WikiADF -Name Trigger1

This command will unsubscribe BlobEnetTrigger1 trigger to the specified events from the trigger definition.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.datafactory/remove-azdatafactoryv2triggersubscription>