



Windows PowerShell Get-Help on Cmdlet 'Remove-AzDataLakeStoreAccount'

PS:\>Get-HELP Remove-AzDataLakeStoreAccount -Full

NAME

Remove-AzDataLakeStoreAccount

SYNOPSIS

Deletes a Data Lake Store account permanently.

SYNTAX

```
Remove-AzDataLakeStoreAccount [-Name] <System.String> [[-ResourceGroupName] <System.String>] [[-Force]]  
[[ -PassThru]] [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

DESCRIPTION

The Remove-AzDataLakeStoreAccount cmdlet deletes a Data Lake Store account permanently.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required?	false
Position?	2
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-Name <System.String>

Specifies the name of the account to remove.

Required?	true
Position?	0
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

-PassThru <System.Management.Automation.SwitchParameter>

Returns an object representing the item with which you are working. By default, this cmdlet does not generate any output.

Required?	false
Position?	3
Default value	False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the resource group that contains the account to remove.

Required? false

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

System.Boolean

NOTES

----- Example 1: Remove a Data Lake Store account -----

Remove-AzDataLakeStoreAccount -Name "ContosoADL"

This command removes the account named ContosoADL from the Data Lake Store.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.datalakestore/remove-azdatalakestoreaccount>

Get-AzDataLakeStoreAccount

New-AzDataLakeStoreAccount

Set-AzDataLakeStoreAccount

Test-AzDataLakeStoreAccount

