



Windows PowerShell Get-Help on Cmdlet 'Remove-AzDataLakeStoreTrustedIdProvider'

PS:\>Get-HELP Remove-AzDataLakeStoreTrustedIdProvider -Full

NAME

Remove-AzDataLakeStoreTrustedIdProvider

SYNOPSIS

Removes the specified trusted identity provider in the specified Data Lake Store.

SYNTAX

```
Remove-AzDataLakeStoreTrustedIdProvider [-Account] <System.String> [[-Name] <System.String>]
[[-ResourceGroupName] <System.String>] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzDataLakeStoreTrustedIdProvider cmdlet removes the specified trusted identity provider in the specified Data Lake Store.

PARAMETERS

-Account <System.String>

The Data Lake Store account to remove the trusted identity provider from

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The name of the trusted identity provider.

Required? false

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Indicates a boolean response should be returned indicating the result of the delete operation.

Required? false

Position? named

Default value False

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of the resource group that contains the account to remove the trusted identity provider from.

Required? false

Position? 4

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

System.Management.Automation.SwitchParameter

OUTPUTS

System.Boolean

NOTES

----- Example 1: Remove a trusted identity provider. -----

Remove-AzDataLakeStoreTrustedIdProvider -AccountName "ContosoADL" -Name MyProvider

Removes the provider "MyProvider" from account "ContosoADL"

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.datalakestore/remove-azdatalakestoretrustedidprovider>

