



## ***Windows PowerShell Get-Help on Cmdlet 'Remove-AzDataProtectionBackupInstance'***

***PS:\>Get-HELP Remove-AzDataProtectionBackupInstance -Full***

### NAME

Remove-AzDataProtectionBackupInstance

### SYNOPSIS

Delete a backupInstances

### SYNTAX

```
Remove-AzDataProtectionBackupInstance -Name <String> -ResourceGroupName <String> [-SubscriptionId <String>]
-VaultName <String> [-Token <String>] [-DefaultProfile
    <PSObject>] [-AsJob] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>]
[-NoWait] [-PassThru] [-Proxy <Uri>] [-ProxyCredential
    <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

```
Remove-AzDataProtectionBackupInstance -InputObject <IDataProtectionIdentity> [-Token <String>] [-DefaultProfile
<PSObject>] [-AsJob] [-Break] [-HttpPipelineAppend
    <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru] [-Proxy <Uri>] [-ProxyCredential
<PSCredential>] [-ProxyUseDefaultCredentials]
    [-WhatIf] [-Confirm] [<CommonParameters>]
```

## DESCRIPTION

Delete a backupInstances

## PARAMETERS

-Name <String>

The name of the backup instance.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

The value must be an UUID.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-VaultName <String>

The name of the backup vault.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IDataProtectionIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-Token <String>

Parameter to authorize operations protected by cross tenant resource guard.

Use command (Get-AzAccessToken -TenantId "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxxx").Token to fetch authorization token for different tenant.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

#### -AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

#### -Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

#### -HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

#### -HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

#### -NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

#### -PassThru [<SwitchParameter>]

Returns true when the command succeeds

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

#### -Proxy <Uri>

The URI for the proxy server to use

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

**-ProxyCredential <PSCredential>**

Credentials for a proxy server to use for the remote call

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

**-ProxyUseDefaultCredentials [<SwitchParameter>]**

Use the default credentials for the proxy

Required? false  
Position? named  
Default value False  
Accept pipeline input? false  
Accept wildcard characters? false

**-WhatIf [<SwitchParameter>]**

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

**-Confirm [<SwitchParameter>]**

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

#### INPUTS

Microsoft.Azure.PowerShell.Cmdlets.DataProtection.Models.IDataProtectionIdentity

#### OUTPUTS

System.Boolean

#### NOTES

#### COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run `Get-Help about_Hash_Tables`.

INPUTOBJECT <IDataProtectionIdentity>: Identity Parameter

[BackupInstanceName <String>]: The name of the backup instance.

[BackupPolicyName <String>]:

[Id <String>]: Resource identity path

[JobId <String>]: The Job ID. This is a GUID-formatted string (e.g. 00000000-0000-0000-0000-000000000000).

[Location <String>]: The location in which uniqueness will be verified.

[OperationId <String>]:

[RecoveryPointId <String>]:

[RequestName <String>]:

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[ResourceGuardProxyName <String>]: name of the resource guard proxy

[ResourceGuardsName <String>]: The name of ResourceGuard

[ResourceId <String>]: ARM path of the resource to be protected using Microsoft.DataProtection

[SubscriptionId <String>]: The ID of the target subscription. The value must be an UUID.

[VaultName <String>]: The name of the backup vault.

#### ----- EXAMPLE 1 -----

```
PS C:\>$instance = Get-AzDataProtectionBackupInstance -SubscriptionId "xxxx-xxx-xxx" -ResourceGroupName  
"MyResourceGroup" -VaultName "MyVault"
```

```
Remove-AzDataProtectionBackupInstance -SubscriptionId "xxxx-xxx-xxx" -ResourceGroupName "MyResourceGroup"  
-VaultName "MyVault" -Name $instance[0].name
```

#### RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.dataprotection/remove-azdataprotectionbackupinstance>