



Windows PowerShell Get-Help on Cmdlet 'Remove-AzDataShare'

PS:\>Get-HELP Remove-AzDataShare -Full

NAME

Remove-AzDataShare

SYNOPSIS

Removes a data share.

SYNTAX

```
Remove-AzDataShare -AccountName <System.String> [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-Name <System.String> [-PassThru] -ResourceGroupName <System.String> [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```
Remove-AzDataShare [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
<Microsoft.Azure.PowerShell.Cmdlets.DataShare.Models.PSDataShare> [-PassThru] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```
Remove-AzDataShare [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
```

-ResourceId

<System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

The Remove-AzDataShare cmdlet removes a data share.

PARAMETERS

-AccountName <System.String>

Azure data share account name

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-AsJob <System.Management.Automation.SwitchParameter>

{{Fill AsJob Description}}

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.PowerShell.Cmdlets.DataShare.Models.PSDataShare>

Azure data share object ``yaml Type: PSDataShare Parameter Sets: ByObjectParameterSet Aliases:

Required: True Position: Named Default value: None Accept pipeline input: True (ByValue) Accept wildcard characters:

False

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Azure data share name

yaml Type: String Parameter Sets: ByFieldsParameterSet Aliases:

Required: True Position: Named Default value: None Accept pipeline input: False Accept wildcard characters: False

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Return object (if specified).

yaml Type: SwitchParameter Parameter Sets: (All) Aliases:

Required: False Position: Named Default value: None Accept pipeline input: False Accept wildcard characters: False

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group name of the azure data share account

yaml Type: String Parameter Sets: ByFieldsParameterSet Aliases:

Required: True Position: Named Default value: None Accept pipeline input: False Accept wildcard characters: False

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ResourceId <System.String>

The resource id of the Azure data share

yaml Type: String Parameter Sets: ByResourceIdParameterSet Aliases:

Required: True Position: Named Default value: None Accept pipeline input: True (ByPropertyName) Accept wildcard characters: False

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

yaml Type: SwitchParameter Parameter Sets: (All) Aliases: cf

Required: False Position: Named Default value: None Accept pipeline input: False Accept wildcard characters: False

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

yaml Type: SwitchParameter Parameter Sets: (All) Aliases: wi

Required: False Position: Named Default value: None Accept pipeline input: False Accept wildcard characters: False

yaml Type: Microsoft.Azure.PowerShell.Cmdlets.DataShare.Models.PSDataShare Parameter Sets:
ByObjectParameterSet Aliases:

Required: True Position: Named Default value: None Accept pipeline input: True (ByValue) Accept wildcard characters:
False

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.PowerShell.Cmdlets.DataShare.Models.PSDataShare

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

Remove-AzDataShare -ResourceGroupName "ADS" -AccountName "WikiAds" -Name "AdsShare"

Are you sure you want to remove data share "AdsShare"?

[Y] Yes [N] No [S] Suspend [?] Help (default is "Y"): Y

This command removes the data share named AdsShare from the azure data share account WikiAds.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.datashare/remove-azdatashare>