



Windows PowerShell Get-Help on Cmdlet 'Remove-AzDnsDnssecConfig'

PS:\>Get-HELP Remove-AzDnsDnssecConfig -Full

NAME

Remove-AzDnsDnssecConfig

SYNOPSIS

Deletes the DNSSEC configuration on a DNS zone.

This operation cannot be undone.

SYNTAX

Remove-AzDnsDnssecConfig -ResourceGroupName <String> [-SubscriptionId <String>] -ZoneName <String> [-IfMatch <String>] [-DefaultProfile <PSObject>] [-AsJob] [-Break]

[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]

[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]

Remove-AzDnsDnssecConfig -InputObject <IDnsIdentity> [-IfMatch <String>] [-DefaultProfile <PSObject>] [-AsJob] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]

[-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]

[<CommonParameters>]

DESCRIPTION

Deletes the DNSSEC configuration on a DNS zone.

This operation cannot be undone.

PARAMETERS

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ZoneName <String>

The name of the DNS zone (without a terminating dot).

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IDnsIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-IfMatch <String>

The etag of this DNSSEC configuration.

Omit this value to always delete the DNSSEC configuration.

Specify the last-seen etag value to prevent accidentally deleting any concurrent changes.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-PassThru [<SwitchParameter>]

Returns true when the command succeeds

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters](https://go.microsoft.com/fwlink/?LinkID=113216) (https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.Dns.Models.IDnsIdentity

OUTPUTS

System.Boolean

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help [about_Hash_Tables](#).

INPUTOBJECT <IDnsIdentity>: Identity Parameter

[Id <String>]: Resource identity path

[RecordType <RecordType?>]: The type of DNS record in this record set.

[RelativeRecordSetName <String>]: The name of the record set, relative to the name of the zone.

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[SubscriptionId <String>]: The ID of the target subscription.

[ZoneName <String>]: The name of the DNS zone (without a terminating dot).

----- EXAMPLE 1 -----

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.dns/remove-azdnssdssecconfig>