



Windows PowerShell Get-Help on Cmdlet 'Remove-AzEnvironment'

PS:\>Get-HELP Remove-AzEnvironment -Full

NAME

Remove-AzEnvironment

SYNOPSIS

Removes endpoints and metadata for connecting to a given Azure instance.

SYNTAX

```
Remove-AzEnvironment [-Name] <System.String> [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Scope  
{Process | CurrentUser}] [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzEnvironment cmdlet removes endpoints and metadata information for connecting to a given Azure instance.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, tenant and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Name <System.String>

Specifies the name of the environment to remove.

Required?	true
Position?	0
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

-Scope <Microsoft.Azure.Commands.Profile.Common.ContextModificationScope>

Determines the scope of context changes, for example, whether changes apply only to the current process, or to all sessions started by this user.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Profile.Models.PSAzureEnvironment

NOTES

----- Example 1: Creating and removing a test environment -----

```
Add-AzEnvironment -Name TestEnvironment `
    -ActiveDirectoryEndpoint TestADEndpoint `
    -ActiveDirectoryServiceEndpointResourceId TestADApplicationId `
    -ResourceManagerEndpoint TestRMEndpoint `
    -GalleryEndpoint TestGalleryEndpoint `
    -GraphEndpoint TestGraphEndpoint
```

Name	Resource Manager Url	ActiveDirectory Authority
TestEnvironment	TestRMEndpoint	TestADEndpoint/

```
Remove-AzEnvironment -Name TestEnvironment
```

Name	Resource Manager Url	ActiveDirectory Authority
TestEnvironment	TestRMEndpoint	TestADEndpoint/

This example shows how to create an environment using Add-AzEnvironment, and then how to delete the environment using Remove-AzEnvironment.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.accounts/remove-azenvironment>

Add-AzEnvironment

Get-AzEnvironment

Set-AzEnvironment