



Windows PowerShell Get-Help on Cmdlet 'Remove-AzExpressRouteCircuitPeeringConfig'

PS:\>Get-HELP Remove-AzExpressRouteCircuitPeeringConfig -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzExpressRouteCircuitPeeringConfig

SYNOPSIS

Removes an ExpressRoute circuit peering configuration.

SYNTAX

```
Remove-AzExpressRouteCircuitPeeringConfig [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-ExpressRouteCircuit <Microsoft.Azure.Commands.Network.Models.PSExpressRouteCircuit> [-Name <System.String>]
[-PeerAddressType {IPv4 | IPv6 | All}]
[<CommonParameters>]
```

DESCRIPTION

The Remove-AzExpressRouteCircuitPeeringConfig cmdlet removes an ExpressRoute circuit peering configuration.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ExpressRouteCircuit <Microsoft.Azure.Commands.Network.Models.PSExpressRouteCircuit>

The ExpressRoute circuit containing the peering configuration to be removed.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

The name of the peering configuration to be removed.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PeerAddressType <System.String>

The Address family of the peering

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSExpressRouteCircuit

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSExpressRouteCircuit

NOTES

Example 1: Remove a peering configuration from an ExpressRoute circuit

```
$circuit = Get-AzExpressRouteCircuit -Name $CircuitName -ResourceGroupName $rg
Remove-AzExpressRouteCircuitPeeringConfig -Name 'AzurePrivatePeering' -ExpressRouteCircuit $circuit
Set-AzExpressRouteCircuit -ExpressRouteCircuit $circuit
```

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/remove-azexpressrouteircuitpeeringconfig>

[Add-AzExpressRouteCircuitPeeringConfig](#)

[Get-AzExpressRouteCircuit](#)

[New-AzExpressRouteCircuitPeeringConfig](#)

[Set-AzExpressRouteCircuit](#)