



Windows PowerShell Get-Help on Cmdlet 'Remove-AzFrontDoor'

PS:\>Get-HELP Remove-AzFrontDoor -Full

NAME

Remove-AzFrontDoor

SYNOPSIS

Remove Front Door load balancer

SYNTAX

```

Remove-AzFrontDoor [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
<Microsoft.Azure.Commands.FrontDoor.Models.PSFrontDoor> [-PassThru] [-Confirm] [-WhatIf] [<CommonParameters>]

Remove-AzFrontDoor [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name <System.String>
[-PassThru]
-ResourceGroupName <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

Remove-AzFrontDoor [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
-ResourceId <System.String>

```

[-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

The Remove-AzFrontDoor cmdlet removes a Front Door load balancer under the current subscription

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.FrontDoor.Models.PSFrontDoor>

The Front Door object to delete.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

The name of the Front Door to delete.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Return object (if specified).

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group to which the Front Door belongs.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

Resource Id of the Front Door to delete

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.FrontDoor.Models.PSFrontDoor

System.String

OUTPUTS

System.Boolean

NOTES

Example 1: Remove "frontdoor1" in resource group "rg1" under the current subscription.

```
Remove-AzFrontDoor -Name "frontdoor1" -ResourceGroupName "rg1"
```

Remove "frontdoor1" in resource group "rg1" under the current subscription.

Example 2: Remove all FrontDoors in resource group "rg1" under the current subscription.

```
Get-AzFrontDoor -ResourceGroupName "rg1" | Remove-AzFrontDoor
```

Remove all FrontDoors in resource group "rg1" under the current subscription.

Example 3: Remove all FrontDoors under the current subscription.

```
Get-AzFrontDoor | Remove-AzFrontDoor
```

Remove all FrontDoors under the current subscription.

Example 4: Remove all FrontDoors with name "frontdoor1" under the current subscription.

```
Remove-AzFrontDoor -Name "frontdoor1" | Remove-AzFrontDoor
```

Remove all FrontDoors with name "frontdoor1" under the current subscription.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.frontdoor/remove-azfrontdoor>

New-AzFrontDoor

Get-AzFrontDoor