



Windows PowerShell Get-Help on Cmdlet 'Remove-AzGalleryImageDefinition'

PS:\>Get-HELP Remove-AzGalleryImageDefinition -Full

NAME

Remove-AzGalleryImageDefinition

SYNOPSIS

Delete a gallery image definition.

SYNTAX

```
Remove-AzGalleryImageDefinition [-ResourceGroupName] <System.String> [-GalleryName] <System.String> [-Name]
<System.String> [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-Confirm]
[-WhatIf] [<CommonParameters>]
```

```
Remove-AzGalleryImageDefinition [-InputObject]
<Microsoft.Azure.Commands.Compute.Automation.Models.PSGalleryImage> [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-Confirm]
[-WhatIf] [<CommonParameters>]
```

```
Remove-AzGalleryImageDefinition [-ResourceId] <System.String> [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-Confirm]
```

[-WhatIf] [<CommonParameters>]

DESCRIPTION

Delete a gallery image definition.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-GalleryName <System.String>

The name of the gallery.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Compute.Automation.Models.PSGalleryImage>

The PS Gallery Image Definition Object

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

The name of the gallery image definition.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

The name of the resource group.

Required? true

Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-ResourceId <System.String>

The resource ID for the gallery image definition

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

Microsoft.Azure.Commands.Compute.Automation.Models.PSGalleryImage

OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSOperationStatusResponse

NOTES

----- Example 1 -----

```
Remove-AzGalleryImageDefinition -ResourceGroupName $rgname -GalleryName $gallery -GalleryImageDefinitionName $galleryImage
```

Remove the gallery image definition.

