



Windows PowerShell Get-Help on Cmdlet 'Remove-AzGalleryImageVersion'

PS:\>Get-HELP Remove-AzGalleryImageVersion -Full

NAME

Remove-AzGalleryImageVersion

SYNOPSIS

Delete a gallery image version.

SYNTAX

```
Remove-AzGalleryImageVersion [-ResourceGroupName] <System.String> [-GalleryName] <System.String>
[-GalleryImageDefinitionName] <System.String> [-Name] <System.String>
                                     [-AsJob]                                     [-DefaultProfile]
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer> [-Force] [-Confirm]
[-WhatIf] [<CommonParameters>]
```

```
Remove-AzGalleryImageVersion                                     [-InputObject]
<Microsoft.Azure.Commands.Compute.Automation.Models.PSGalleryImageVersion> [-AsJob] [-DefaultProfile]
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer> [-Force] [-Confirm]
[-WhatIf] [<CommonParameters>]
```

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-Confirm]
[-WhatIf] [<CommonParameters>]

DESCRIPTION

Delete a gallery image version.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-GalleryImageDefinitionName <System.String>

The name of the gallery image definition.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-GalleryName <System.String>

The name of the gallery.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Compute.Automation.Models.PSGalleryImageVersion>

The PS Gallery Image Version Object

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

The name of the gallery image version.

Required? true
Position? 3
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-ResourceGroupName <System.String>

The name of the resource group.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-ResourceId <System.String>

The resource ID for gallery image version

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.Compute.Automation.Models.PSGalleryImageVersion

OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSOperationStatusResponse

NOTES

----- Example 1 -----

```
Remove-AzGalleryImageVersion -ResourceGroupName $rgname -GalleryName $gallery -GalleryImageDefinitionName  
$image -Name $version
```

Delete the given gallery image version.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/remove-azgalleryimageversion>