



Windows PowerShell Get-Help on Cmdlet 'Remove-AzIntegrationAccountMap'

PS:\>Get-HELP Remove-AzIntegrationAccountMap -Full

NAME

Remove-AzIntegrationAccountMap

SYNOPSIS

Removes an integration account map.

SYNTAX

```
Remove-AzIntegrationAccountMap [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -MapName  
<System.String> -Name <System.String> -ResourceGroupName <System.String> [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

DESCRIPTION

The Remove-AzIntegrationAccountMap cmdlet removes an integration account map from a resource group. Specify the integration account name, resource group name, and map

name. This module supports dynamic parameters. To use a dynamic parameter, type it in the command. To discover the names of dynamic parameters, type a hyphen (-)

after the cmdlet name, and then press the Tab key repeatedly to cycle through the available parameters. If you omit a

required template parameter, the cmdlet prompts

you for the value.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-MapName <System.String>

Specifies the name of the integration account map.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the integration account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of a resource group.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

System.Void

NOTES

----- Example 1: Remove an integration account map -----

```
Remove-AzIntegrationAccountMap -ResourceGroupName "ResourceGroup11" -Name "IntegrationAccount31"
-MapName "IntegrationAccountMap47"
```

This command removes the integration account map named IntegrationAccountMap47.

Online Version: <https://learn.microsoft.com/powershell/module/az.logicapp/remove-azintegrationaccountmap>

Get-AzIntegrationAccountMap

New-AzIntegrationAccountMap

Set-AzIntegrationAccountMap