



Windows PowerShell Get-Help on Cmdlet 'Remove-AzlotHubRoutingEndpoint'

PS:\>Get-HELP Remove-AzlotHubRoutingEndpoint -Full

NAME

Remove-AzlotHubRoutingEndpoint

SYNOPSIS

Delete an endpoint for your IoT Hub

SYNTAX

```
Remove-AzlotHubRoutingEndpoint [-InputObject] <Microsoft.Azure.Commands.Management.IotHub.Models.PSIotHub>
[-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-EndpointName
<System.String>] [-EndpointType {EventHub | ServiceBusQueue
| ServiceBusTopic | AzureStorageContainer}] [-PassThru] [-Confirm] [-WhatIf] [<CommonParameters>]

Remove-AzlotHubRoutingEndpoint [-ResourceGroupName] <System.String> [-Name] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-EndpointName
<System.String>] [-EndpointType {EventHub | ServiceBusQueue
| ServiceBusTopic | AzureStorageContainer}] [-PassThru] [-Confirm] [-WhatIf] [<CommonParameters>]
```

Remove-AzlotHubRoutingEndpoint [-ResourceId] <System.String> [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-EndpointName
<System.String>] [-EndpointType {EventHub | ServiceBusQueue
| ServiceBusTopic | AzureStorageContainer}] [-PassThru] [-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

Delete an endpoint. Remember to delete any routes that use this endpoint.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-EndpointName <System.String>

Name of the Routing Endpoint

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-EndpointType <Microsoft.Azure.Commands.Management.IotHub.Models.PSEndpointType>

Type of the Routing Endpoint

Required? false

Position? named

Default value None
Accept pipeline input? False
Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Management.IotHub.Models.PSIotHub>

IotHub Object

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Name <System.String>

Name of the Iot Hub

Required? true
Position? 1
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Allows to return the boolean object. By default, this cmdlet does not generate any output.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of the Resource Group

Required? true
Position? 0
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ResourceId <System.String>

IoT Hub Resource Id

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.Management.IotHub.Models.PSlotHub

System.String

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

```
Remove-AzIotHubRoutingEndpoint -ResourceGroupName "myresourcegroup" -Name "myiothub" -EndpointName E2  
-PassThru
```

True

Delete endpoint "E2" from "myiothub" IoT Hub.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.iothub/remove-aziothubroutindingendpoint>