



Windows PowerShell Get-Help on Cmdlet 'Remove-AzLoadBalancerBackendAddressPoolConfig'

PS:\>Get-HELP Remove-AzLoadBalancerBackendAddressPoolConfig -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzLoadBalancerBackendAddressPoolConfig

SYNOPSIS

Removes a backend address pool configuration from a load balancer.

SYNTAX

```

Remove-AzLoadBalancerBackendAddressPoolConfig [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-LoadBalancer <Microsoft.Azure.Commands.Network.Models.PSLoadBalancer> [-Name <System.String>] [-Confirm]
[-WhatIf] [<CommonParameters>]

```

DESCRIPTION

The Remove-AzLoadBalancerBackendAddressPoolConfig cmdlet removes a backend address pool from a load balancer.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-LoadBalancer <Microsoft.Azure.Commands.Network.Models.PSLoadBalancer>

Specifies the load balancer that contains the backend address pool to remove.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the backend address pool that this cmdlet removes.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

NOTES

Example 1: Remove a backend address pool configuration from a load balancer

```
Get-AzLoadBalancer -Name "MyLoadBalancer" -ResourceGroupName "MyResourceGroup" |  
Remove-AzLoadBalancerBackendAddressPoolConfig -Name "BackendAddressPool02" |  
Set-AzLoadBalancer
```

This command gets the load balancer named MyLoadBalancer and passes it to Remove-AzLoadBalancerBackendAddressPoolConfig , which removes the BackendAddressPool02 configuration from MyLoadBalancer. Finally, the Set-AzLoadBalancer cmdlet updates MyLoadBalancer. Note that a backend address pool configuration must exist before you can delete it.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.network/remove-azloadbalancerbackendaddresspoolconfig>

Add-AzLoadBalancerBackendAddressPoolConfig

Get-AzLoadBalancer

Get-AzLoadBalancerBackendAddressPoolConfig

New-AzLoadBalancerBackendAddressPoolConfig