



Windows PowerShell Get-Help on Cmdlet 'Remove-AzLoadBalancerFrontendIpConfig'

PS:\>Get-HELP Remove-AzLoadBalancerFrontendIpConfig -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzLoadBalancerFrontendIpConfig

SYNOPSIS

Removes a front-end IP configuration from a load balancer.

SYNTAX

```
Remove-AzLoadBalancerFrontendIpConfig [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -LoadBalancer
<Microsoft.Azure.Commands.Network.Models.PSLoadBalancer> [-Name <System.String>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

The Remove-AzLoadBalancerFrontendIpConfig cmdlet removes a front-end IP configuration from an Azure load balancer.

balancer.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-LoadBalancer <Microsoft.Azure.Commands.Network.Models.PSLoadBalancer>

Specifies the load balancer that contains the front-end IP configuration to remove.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the front-end IP address configuration to remove.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

Example 1: Remove a front-end IP configuration from a load balancer

```
$loadbalancer = Get-AzLoadBalancer -Name "MyLoadBalancer" -ResourceGroupName "MyResourceGroup"  
Remove-AzLoadBalancerFrontendIpConfig -Name "frontendName" -LoadBalancer $loadbalancer
```

The first command gets the load balancer that is associated with the front-end IP configuration you want to remove, and then stores it in the `$loadbalancer` variable.

The second command removes the associated frontend IP configuration from the load balancer in `$loadbalancer`.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/remove-azloadbalancerfrontendipconfig>

[Add-AzLoadBalancerFrontendIpConfig](#)

[Get-AzLoadBalancer](#)

[Get-AzLoadBalancerFrontendIpConfig](#)

[New-AzLoadBalancerFrontendIpConfig](#)

[Set-AzLoadBalancerFrontendIpConfig](#)