



Windows PowerShell Get-Help on Cmdlet 'Remove-AzLoadBalancerProbeConfig'

PS:\>Get-HELP Remove-AzLoadBalancerProbeConfig -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzLoadBalancerProbeConfig

SYNOPSIS

Removes a probe configuration from a load balancer.

SYNTAX

```
Remove-AzLoadBalancerProbeConfig [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -LoadBalancer  
    <Microsoft.Azure.Commands.Network.Models.PSLoadBalancer> [-Name <System.String>] [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

DESCRIPTION

The Remove-AzLoadBalancerProbeConfig cmdlet removes a probe configuration from a load balancer.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-LoadBalancer <Microsoft.Azure.Commands.Network.Models.PSLoadBalancer>

Specifies the load balancer that contains the probe configuration that this cmdlet removes.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the probe configuration that this cmdlet removes.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

NOTES

- Example 1: Remove a probe configuration from a load balancer -

```
$loadbalancer = Get-AzLoadBalancer -Name "MyLoadBalancer" -ResourceGroupName "MyResourceGroup"  
Remove-AzLoadBalancerProbeConfig -Name "MyProbe" -LoadBalancer $loadbalancer
```

The first command gets the load balancer named MyLoadBalancer, and then stores it in the \$loadbalancer variable. The second command deletes the configuration named MyProbe from the load balancer in \$loadbalancer.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/remove-azloadbalancerprobeconfig>

Add-AzLoadBalancerProbeConfig

Get-AzLoadBalancer

Get-AzLoadBalancerProbeConfig

New-AzLoadBalancerProbeConfig

Set-AzLoadBalancerProbeConfig