



Windows PowerShell Get-Help on Cmdlet 'Remove-AzMaintenanceConfiguration'

PS:\>Get-HELP Remove-AzMaintenanceConfiguration -Full

NAME

Remove-AzMaintenanceConfiguration

SYNOPSIS

Delete Configuration record

SYNTAX

```
Remove-AzMaintenanceConfiguration [-ResourceGroupName] <System.String> [-Name] <System.String> [-AsJob]
[-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

Delete Maintenance Configuration record

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Force <System.Management.Automation.SwitchParameter>

Force remove without confirmation.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-Name <System.String>

The maintenance configuration Name.

Required?	true
Position?	1
Default value	None
Accept pipeline input?	True (ByPropertyName)

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Returns the status of the Remove operation. By default, this cmdlet does not generate any output.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource Group Name.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

Remove-AzMaintenanceConfiguration -ResourceGroupName smdtest -Name workervmscentralus

Remove-AzMaintenanceConfiguration operation

This cmdlet will remove the specified resource. Do you want to continue?

[Y] Yes [N] No [S] Suspend [?] Help (default is "Y"):

Delete Maintenance Configuration record

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.maintenance/remove-azmaintenanceconfiguration>