



Windows PowerShell Get-Help on Cmdlet 'Remove-AzNatGateway'

PS:\>Get-HELP Remove-AzNatGateway -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzNatGateway

SYNOPSIS

Remove Nat Gateway resource.

SYNTAX

Remove-AzNatGateway [-AsJob] [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -InputObject

<Microsoft.Azure.Commands.Network.Models.PSNatGateway> [-PassThru] [-Confirm] [-WhatIf] [<CommonParameters>]

Remove-AzNatGateway [-AsJob] [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -Name

<System.String> [-PassThru] -ResourceGroupName <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
-ResourceId <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

Remove Nat Gateway Resource

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Do not ask for confirmation if you want to delete resource.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Network.Models.PSNatGateway>

Specifies the Nat Gateway resource.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Name of the Nat Gateway resource.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Returns an object representing the item with which you are working. By default, this cmdlet does not generate any output.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of the Resource Group.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

Resource Id associated with the Nat Gateway.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSNatGateway

System.String

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

```
$nat = Get-AzNatGateway -ResourceGroupName "natgateway_test" -Name "nat_gateway"
```

```
Remove-AzNatGateway -InputObject $nat
```

Remove-AzNatGateway

-ResourceId

"/subscriptions/<subid>/resourceGroups/natgateway_test/providers/Microsoft.Network/natGateways/natgateway"

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/remove-aznatgateway>