



### ***Windows PowerShell Get-Help on Cmdlet 'Remove-AzNetworkCloudServicesNetwork'***

***PS: \>Get-HELP Remove-AzNetworkCloudServicesNetwork -Full***

WARNING: The names of some imported commands from the module 'Az.NetworkCloud.private' include unapproved verbs that might make them less discoverable. To find the

commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

WARNING: The names of some imported commands from the module 'Az.NetworkCloud.private' include unapproved verbs that might make them less discoverable. To find the

commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

WARNING: The names of some imported commands from the module 'Az.NetworkCloud.private' include unapproved verbs that might make them less discoverable. To find the

commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

#### **NAME**

Remove-AzNetworkCloudServicesNetwork

#### **SYNOPSIS**

Delete the provided cloud services network.

#### **SYNTAX**

```
Remove-AzNetworkCloudServicesNetwork -Name <String> -ResourceGroupName <String> [-SubscriptionId <String>]
[-DefaultProfile <PSObject>] [-AsJob] [-Break]

[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru] [-Proxy
<Uri>] [-ProxyCredential <PSCredential>]

[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

```
Remove-AzNetworkCloudServicesNetwork -InputObject <INetworkCloudIdentity> [-DefaultProfile <PSObject>] [-AsJob]
[-Break] [-HttpPipelineAppend <SendAsyncStep[]>]

[-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]

[<CommonParameters>]
```

## DESCRIPTION

Delete the provided cloud services network.

## PARAMETERS

**-Name <String>**

The name of the cloud services network.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

**-ResourceGroupName <String>**

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

#### -SubscriptionId <String>

The ID of the target subscription.

The value must be an UUID.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

#### -InputObject <INetworkCloudIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

#### -DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

**-NoWait [<SwitchParameter>]**

Run the command asynchronously

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

**-PassThru [<SwitchParameter>]**

Returns true when the command succeeds

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

**-Proxy <Uri>**

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

**-ProxyCredential <PSCredential>**

Credentials for a proxy server to use for the remote call

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false  
Position? named  
Default value False  
Accept pipeline input? false  
Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

## INPUTS

Microsoft.Azure.PowerShell.Cmdlets.NetworkCloud.Models.INetworkCloudIdentity

## OUTPUTS

System.Boolean

## NOTES

### COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run `Get-Help about_Hash_Tables`.

INPUTOBJECT <INetworkCloudIdentity>: Identity Parameter

[AgentPoolName <String>]: The name of the Kubernetes cluster agent pool.

[BareMetalMachineKeySetName <String>]: The name of the bare metal machine key set.

[BareMetalMachineName <String>]: The name of the bare metal machine.

[BmcKeySetName <String>]: The name of the baseboard management controller key set.

[CloudServicesNetworkName <String>]: The name of the cloud services network.

[ClusterManagerName <String>]: The name of the cluster manager.

[ClusterName <String>]: The name of the cluster.

[ConsoleName <String>]: The name of the virtual machine console.

[Id <String>]: Resource identity path

[KubernetesClusterName <String>]: The name of the Kubernetes cluster.

[L2NetworkName <String>]: The name of the L2 network.

[L3NetworkName <String>]: The name of the L3 network.

[MetricsConfigurationName <String>]: The name of the metrics configuration for the cluster.

[RackName <String>]: The name of the rack.

[RackSkuName <String>]: The name of the rack SKU.

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[StorageApplianceName <String>]: The name of the storage appliance.

[SubscriptionId <String>]: The ID of the target subscription. The value must be an UUID.

[TrunkedNetworkName <String>]: The name of the trunked network.

[VirtualMachineName <String>]: The name of the virtual machine.

[VolumeName <String>]: The name of the volume.

#### ----- EXAMPLE 1 -----

```
PS C:\>Remove-AzNetworkCloudServicesNetwork -ResourceGroupName resourceGroupName  
-CloudServicesNetworkName cloudNetworkServicesName -SubscriptionId subscriptionId
```

#### RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.networkcloud/remove-aznetworkcloudservicesnetwork>