



Windows PowerShell Get-Help on Cmdlet 'Remove-AzNetworkManagerConnectivityConfiguration'

PS: \> Get-HELP Remove-AzNetworkManagerConnectivityConfiguration -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzNetworkManagerConnectivityConfiguration

SYNOPSIS

Removes a connectivity configuration.

SYNTAX

```
Remove-AzNetworkManagerConnectivityConfiguration [-AsJob] [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]  
[-Force] [-ForceDelete] -Name <System.String> -NetworkManagerName <System.String> [-PassThru]  
-ResourceGroupName <System.String> [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

DESCRIPTION

The Remove-AzNetworkManagerConnectivityConfiguration cmdlet removes a connectivity configuration.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Do not ask for confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ForceDelete <System.Management.Automation.SwitchParameter>

Deletes the resource even if it is deployed. If the configuration has been deployed, the service will do a cleanup

deployment in the background, prior to the
delete.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-Name <System.String>

The resource name.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

-NetworkManagerName <System.String>

The network manager name.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	true

-PassThru <System.Management.Automation.SwitchParameter>

{{ Fill PassThru Description }}

Required?	false
Position?	named
Default value	False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group name.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

```
Remove-AzNetworkManagerConnectivityConfiguration -Name TestConnConfigName -NetworkManagerName  
TestNMName -ResourceGroupName TestRGName -ForceDelete
```

Removes a connectivity configuration.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.network/remove-aznetworkmanagerconnectivityconfiguration>

New-AzNetworkManagerConnectivityConfiguration

Get-AzNetworkManagerConnectivityConfiguration

Set-AzNetworkManagerConnectivityConfiguration

