



Windows PowerShell Get-Help on Cmdlet 'Remove-AzNginxConfiguration'

PS:\>Get-HELP Remove-AzNginxConfiguration -Full

NAME

Remove-AzNginxConfiguration

SYNOPSIS

Reset the NGINX configuration of given NGINX deployment to default

SYNTAX

```
Remove-AzNginxConfiguration -DeploymentName <String> -Name <String> -ResourceGroupName <String>
[-SubscriptionId <String>] [-DefaultProfile <PSObject>] [-AsJob]
[-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru]
[-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

```
Remove-AzNginxConfiguration -InputObject <INginxIdentity> [-DefaultProfile <PSObject>] [-AsJob] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-NoWait] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Reset the NGINX configuration of given NGINX deployment to default

PARAMETERS

-DeploymentName <String>

The name of targeted NGINX deployment

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Name <String>

The name of configuration, only 'default' is supported value due to the singleton of NGINX conf

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <INginxIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

-PassThru [<SwitchParameter>]

Returns true when the command succeeds

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

-Proxy <Uri>

The URI for the proxy server to use

Required?	false
Position?	named
Default value	
Accept pipeline input?	false
Accept wildcard characters?	false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required?	false
Position?	named
Default value	
Accept pipeline input?	false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.Nginx.Models.INginxIdentity

OUTPUTS

System.Boolean

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

about_Hash_Tables.

INPUTOBJECT <INginxIdentity>: Identity Parameter

[CertificateName <String>]: The name of certificate

[ConfigurationName <String>]: The name of configuration, only 'default' is supported value due to the singleton of NGINX conf

[DeploymentName <String>]: The name of targeted NGINX deployment

[Id <String>]: Resource identity path

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[SubscriptionId <String>]: The ID of the target subscription.

----- EXAMPLE 1 -----

PS C:\>Remove-AzNginxConfiguration -DeploymentName nginx-test -Name default -ResourceGroupName nginx-test-rg

----- EXAMPLE 2 -----

```
PS C:\>Get-AzNginxConfiguration -DeploymentName nginx-test -Name default -ResourceGroupName nginx-test-rg |  
Remove-AzNginxConfiguration
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.nginx/remove-aznginxconfiguration>